




Temperature Update






Initiate a Sleep





Various Requests




Further Requests









Thermistor

The Thermistor firmware is capable of operating as a permanently powered "polled" device or a cyclic "sleeping" device more suited to battery applications.

The supported commands for the temp firmware are:

Generic commands

- APVER - LLAP version
- DEVTTYPE - Device type
- DEVNAME - Device name
- HELLO - Hello (PING)
- SER - Serial number
- FVER - Firmware version
- CHDEVID - Change device ID
- PANID - Change PANID
- REROOT - Restart the device
- INTVLXXXX - Sets the interval for reading the temperature - 9995 would be 999 seconds - T=ms, S=secs, M=mins, H=hours, D=Days - Once the command is sent the device will begin to send readings at the frequency requested. Whilst you are testing it's useful not to yet issue CYCLE, once asleep it's not an easy task to wake it.
- CYCLE - Activate cyclic sleeping, the device will wake every INTVL - Once this command has been issued the device will remain asleep for the majority of the time. Whilst asleep everything is turned off, that includes the radio.
- WAKE

Device specific commands

- TMPA - Reply with the temperature
- TEMP - Reply with the temperature
- BVALXXXX sets the B coefficient for the simplified Steinhart equation (default aXXBVAL3977)
- RNDMXXXX sets the Thermistor resistance at 25 degrees c (default aXXRNDM10000)
- SRESXXXX sets the series resistor value (default aXXSRES10000)
- IRESXXXX sets the Analog input resistance (default aXXIRES5000) you should not normally change this.

Battery voltage

In cyclic sleeping mode, the battery voltage is broadcast every 10 readings. The voltage is read at the point of transmission so is always lower than the battery "at rest".

DALLAS

The Dallas firmware is capable of operating as a permanently powered "polled" device with 1 Dallas DS18B20 sensors connected. Looking at the datasheet for the DS18B20 and the CC1110 a voltage of between 3v and 3.6v should suffice. A nominal voltage of 3.3v would be best.

The supported commands for the temp firmware are:

Generic commands

- APVER - LLAP version
- DEVTYPE - Device type
- DEVNAME - Device name
- HELLO - Hello (PING)
- SER - Serial number
- FVER - Firmware version
- CHDEVID - Change device ID
- PANID - Change PANID
- REBOOT - Restart the device

Device specific commands

- TEMP - Reply with the temperature on channel A
- TMPA - Reply with the temperature on channel A

Please note:

Dallas temperature sensors do not lend themselves to low power broadcasts so cyclic sleep is not implemented on the Dallas firmware

However like most device the Dallas does support the polled Sleep command (SLEEP9999) details can be found [here](#)

Trouble shooting

If the reading comes back as 127 degrees then the XRF is talking to the sensor but the actual sensor has failed to do a temp conversion, this can be because the supply voltage is not high enough

LIGHT DEPENDENT RESISTOR

The LDR firmware is capable of operating as a permanently powered "polled" device or a cyclic "sleeping" device more suited to battery applications. Readings are taken from a Light Dependent Resistor and vary from 0 (no light) to 99 (full bright light)

The supported commands for the temp firmware are:

Generic commands

- APVER - LLAP version
- DEVTYPE - Device type
- DEVNAME - Device name
- HELLO - Hello (PING)
- SER - Serial number
- FVER - Firmware version
- CHDEVID - Change device ID
- PANID - Change PANID
- REBOOT - Restart the device
- INTVLxxxx - Sets the interval for reading the temperature - 999S would be 999 seconds - T=ms, S=secs, M=mins, H=hours, D=Days - Once the command is sent the device will begin to send readings at the frequency requested. Whilst you are testing it's useful not to yet issue CYCLE, once asleep it's not an easy task to wake it
- CYCLE - Activate cyclic sleeping, the device will wake every INTVL - Once this command has been issued the device will remain asleep for the majority of the time. Whilst asleep everything is turned off, that includes the radio

Device specific commands


- LVAL - Reply with the light level from 0 to 99

↓ response = id =
message.devtype
DEVTYPE →
A-- DEVTYPE ←


if message.devtype = devtype

registru

Personality	1	AD	7
Personality	2	AB	7
registrar		Regis	



So the question is
can I stop this
sequence with an
external command.



store device specific data.

use kvp's

← can't be another looking.

deviceid, keyid, value.

↑

keys

